



DECUS

PROGRAM LIBRARY

DECUS NO.	8-196
TITLE	DET - DETECT KEY WORDS
AUTHOR	S. G. Cannon
COMPANY	UNIVAC Salt Lake City, Utah
DATE	October 10, 1968
SOURCE LANGUAGE	PAL III

DET - DETECT KEY WORDS

DECUS Program Library Write-up

DECUS No. 8-196

DET will detect a key word or words from any sentence that is typed in. Upon detection the program will execute the JMP instruction that is associated with that key. All other words in the sentence will not be effected so that any arrangement of words can be used. A basic "Conversation" tupe routine called "SPELL" is included to demonstrate the program operation. "FOCAL" was not used so as to have as much space possible for key words and answers.

"DET" is linked to gether with a "REPLY" program. REPLY randomly selects an answer from a specific class of answers, i.e.

1. The key word selects an answer from a class
2. A random number selects a sentence from a class
3. A format number selects classes of words for the sentence
4. A random number selects a word for each word class (variable word) within the sentence, this allows for a vast combination of replies to key words.

OPERATION

1. Load the program with bin loader.
2. Start at address 0200.
3. Type in any sentence which includes key word or words, followed by a space and a carriage return.
4. If two key words are included, it will only detect the last one.
5. If key word is misspelled it will not detect it.

NOTE: Not all the states have been included in the "SPELL" program. The only key word not a state is "DUMB."

TYPEOUT FOR "SPELL" ROUTINE

IS THIS HOW TO SPELL UTAH ?
THAT IS CORRECT

IS THE STATE OF UTAH SPELLED LIKE THIS ?
THAT IS CORRECT

DOES THIS SPELL MASSACHUSETTS ?
YOU ARE A GENIUS

DOES THIS SPELL MASSACHUSETS ?
YOU GOOFED TRY AGAIN

IS THE STATE OF PENNSYLVANNIA SPELLED OK
YOU GOOFED TRY AGAIN

HOW ABOUT SPELLING PENNSYLVANIA THI WAY
THAT IS PRETTY GOOD SPELLING

HOW ABOUT ALASKA
YOU GOOFED TRY AGAIN (NOT IN STORAGE)

HOW CAN YOU BE SO DUMB
DO YOU HATE ME

OHIO
THAT IS CORRECT

WYOMING
THAT IS PRETTY GOOD SPELLING

OHIO AND WYOMING
THAT IS PRETTY GOOD SPELLING

WYOMING AND OHIO
THAT IS CORRECT

WYEOMING AND OHIO
THAT IS CORRECT

WYOMING AND OHIO
THAT IS PRETTY GOOD SPELLING

WYOMING AND MASSACHUSETS
THAT IS PRETTY GOOD SPELLING

WYOMING AND MASSACHUUSSEETS
THAT IS PRETTY GOOD SPELLING

Last Key Word is Detected Only

Only One Key Word

"SPELL" PROGRAM

0200	7240	0361	3360	6032
0204	6031	5204	6034	3362
0210	7240	0362	3764	2364
0214	6042	7240	0362	6044 7000
0220	6041	5220	7240	0362
0224	1370	7040	7440	5203
0230	7240	0365	3364	7240
0234	0367	3366	7240	0764
0240	3362	2364	7240	0362
0244	1370	7040	7440	5251
0250	5354	2366	7240	0766
0254	3363	7240	0363	7440
0260	5262	5251	7240	0763
0264	7440	5275	7240	0362
0270	1371	7040	7440	5233
0274	5334	7240	0763	1372
0300	7040	7440	5305	2362
0304	5323	7240	0763	7040
0310	1362	7040	7440	5325
0314	7240	0763	1371	7040
0320	7440	5323	5330	2766
0324	5251	7200	3766	5251
0330	2363	7240	0763	3360
0334	7240	0773	3775	2373
0340	2375	7240	0773	7440
0344	5334	7240	0374	3373
0350	7240	0376	3375	5233
0354	7240	0365	3364	5760
0360	0614	0614	0215	2344
0364	0100	0100	0477	0477
0370	7562	7537	0777	1025
0374	1025	1000	1000	0000

"DET"

THIS IS THE "DET" DETECT PROGRAM
INCLUDED IN "SPELL"

KOUB

366 = 0777
367 = 0777

SPACE AFTER LAST WORD!

0500	0200	2360	7200	1760
0504	7440	5307	5700	7200
0510	1760	1361	7440	5316
0514	1760	5353	7200	1760
0520	1362	7440	5325	1760
0524	5353	7200	1760	1363
0530	7440	5334	1760	5353
0534	7200	1760	7012	7012
0540	7012	0364	1365	6044
0544	6041	5344	6042	7200
0550	1760	0364	1365	6044 6046
0554	6041	5354	6042	5301
0560	0000	7563	7566	7540
0564	0077	0300		

"TOW.II"

(TO CHECK "DET" → 0501 = 7402)


0600	(1372 3623 5622)	1373
0604	3623 5622	1374 3623
0610	5622 1375	3623 5622
0614	(1376 3623 5622)	1377
0620	3623 5622	0501 0560
0624	0000 0212	2701 2403
0630	1077 0240	3117 2522
0634	0240 1401	1607 2501
0640	0705 0240	0215 0212
0644	0000 0212	0417 0240
0650	3117 2577	0240 1001
0654	2405 0240	1505 0240
0660	0215 0212	0000 0000


"TOW.II" CLINK

- WATCH YOUR LANGUAGE

"TOW.II" FONT

"DET"





1. USE "DET" AND VARIABLE DATA C (HAND LOAD 2nd PART)

OR

2. USE "SPELL" WHICH INCLUDES "DET" (TAPE PROVIDED)

"DET" INSTRUCTIONS

*0200				
0200	7240	BEGN,	STA	
0201	0361		AND	RJUM /RESET FOR DON'T UNDERSTAND
0202	3360		DCA	JUMP
0203	6032	STAR,	KCC	/CLEAR FLAG AND ACC
0204	6031	WAIT,	KSF	/SKIP IF FLAG
0205	5204		JMP	WAIT /JUMP WAIT
0206	6034		KRS	/READ KEY TO ACC
0207	3362		DCA	CHAR
0210	7240		STA	
0211	0362		AND	CHAR
0212	3764		DCA	I KOUA /DEP EACH CHAR IN SENTENCE AREA "A"
0213	2364		ISZ	KOUA /INCREMENT AREA "A" COUNTER
0214	6042		TCF	/CLR FLAG AND ACC
0215	7240		STA	
0216	0362		AND	CHAR
0217	6044		TPC	/ECHO PRINT THE INPUT
0220	6041	WOAH,	TSF	/SKIP IF FLAG
0221	5220		JMP	WOAH /JUMP WAIT
0222	7240		STA	
0223	0362		AND	CHAR
0224	1370		TAD	MASA /INPUT CHARACTER
0225	7040		CMA	/ADD MASK (7562) CAR RET
0226	7440		SZA	/ZERO=CAR RET=SENTENCE END
0227	5203		JMP	STAR /RETURN FOR NEXT CHARACTER
0230	7240		STA	
0231	0365		AND	RSKA
0232	3364		DCA	KOUA /RESTORE AREA "A" COUNTER
0233	7240	NEXT,	STA	
0234	0367		AND	RSKB
0235	3366		DCA	KOUB /RESTORE KEY CHARACTER COUNTER
0236	7240		STA	
0237	0764		AND	I KOUA
0240	3362		DCA	CHAR /BRING OUT INPUT CHAR FOR COMPARE
0241	2364		ISZ	KOUA /INCREMENT AREA "A" COUNTER
0242	7240		STA	
0243	0362		AND	CHAR
0244	1370		TAD	MASA /ADD MASK (7562) CAR RET
0245	7040		CMA	
0246	7440		SZA	/ZERO=CAR RET=SEARCH END
0247	5251		JMP	KEYS
0250	5354		JMP	OUTS /END OF SEARCH-NEXT ROUTINE
0251	2366	KEYS,	ISZ	KOUB /INCREMENT AREA "B" COUNTER (START ■)
0252	7240		STA	
0253	0766		AND	I KOUB
0254	3363		DCA	INDI /BRING OUT KEY CHARACTER FOR COMPARE
0255	7240		STA	
0256	0363		AND	INDI
0257	7440		SZA	/HOLDS ADRSS OF KEY CHARACTER
				/ZERO=NOT A KEY WORD

Ø26Ø	5262		JMP	ZERO	
Ø261	5251		JMP	KEYS	/NEXT KEY CHARACTER
Ø262	724Ø	ZERO,	STA		
Ø263	Ø763		AND I	INDI	
Ø264	744Ø		SZA		/ZERO=END OF KEY WORDS
Ø265	5275		JMP	DUAL	
Ø266	724Ø		STA		
Ø267	Ø362		AND	CHAR	
Ø27Ø	1371		TAD	MASB	/ADD MASK (7537) SPACE
Ø271	7Ø4Ø		CMA		
Ø272	744Ø		SZA		/ZERO=SPACE=END OF INPUT WORD
Ø273	5233		JMP	NEXT	
Ø274	5334		JMP	REST	
Ø275	724Ø	DUAL,	STA		
Ø276	Ø763		AND I	INDI	/TEST IF DUAL WORD
Ø277	1372		TAD	MASC	
Ø3ØØ	7Ø4Ø		CMA		
Ø3Ø1	744Ø		SZA		/ZERO INDICATES DUAL KEY WORD
Ø3Ø2	53Ø5		JMP	CONT	
Ø3Ø3	2362		ISZ	CHAR	/INCREMENT TO SKIP SPACE
Ø3Ø4	5323		JMP	OKAY	
Ø3Ø5	724Ø	CONT,	STA		
Ø3Ø6	Ø763		AND I	INDI	/KEY CHARACTER FOR COMPARE
Ø3Ø7	7Ø4Ø		CMA		
Ø31Ø	1362		TAD	CHAR	/INPUT CHARACTER FOR COMPARE
Ø311	7Ø4Ø		CMA		
Ø312	744Ø		SZA		/ZERO=INDI AND CHAR COMPARE
Ø313	5325		JMP	BAAD	/NOT A KEY WORD
Ø314	724Ø		STA		
Ø315	Ø763		AND I	INDI	
Ø316	1371		TAD	MASB	/ADD MASK (7537) SPACE
Ø317	7Ø4Ø		CMA		
Ø32Ø	744Ø		SZA		/ZERO=SPACE=GOOD KEY WORD
Ø321	5323		JMP	OKAY	
Ø322	533Ø		JMP	GOOD	
Ø323	2766	OKAY,	ISZ I	KOUB	/INCREMENT PRESENT KEY COUNTER
Ø324	5251		JMP	KEYS	/NEXT KEY WORD
Ø325	72ØØ	BAAD,	CLA		
Ø326	3766		DCA I	KOUB	/CLEAR COUNTER
Ø327	5251		JMP	KEYS	/NEXT KEY WORD
Ø33Ø	2363	GOOD,	ISZ	INDI	/INCREMENT KEY COUNT
Ø331	724Ø		STA		
Ø332	Ø763		AND I	INDI	
Ø333	336Ø		DCA	JUMP	/LOAD JUMP FOR OUTPUT TO SUBROUTINE
Ø334	724Ø	REST,	STA		/TO RESET THE KEY CHAR COUNTERS
Ø335	Ø773		AND I	KOUC	
Ø336	3775		DCA I	KOUD	/RESET EACH COUNTER
Ø337	2373		ISZ	KOUC	/INCREMENT COUNTER

Ø34Ø 2375		ISZ	KOUD	/INCREMENT COUNTER
Ø341 724Ø		STA		
Ø342 Ø773		AND I	KOUC	/TO CHECK IF ALL WORDS TRANSFERRED
Ø343 744Ø		SZA		/ZERO=END OF TRANSFER
Ø344 5334		JMP	REST	
Ø345 724Ø		STA		
Ø346 Ø374		AND	RSKC	
Ø347 3373		DCA	KOUC	/RESET KOUC
Ø35Ø 724Ø		STA		
Ø351 Ø376		AND	RSKD	
Ø352 3375		DCA	KOUD	/RESET KOUD
Ø353 5233		JMP	NEXT	/NEXT INPUT CHARACTER
Ø354 724Ø	OUTS,	STA		
Ø355 Ø365		AND	RSKA	
Ø356 3364		DCA	KOUA	/RESET AREA "A" COUNTER
Ø357 576Ø		JMP I	JUMP	/TO NEXT SUBROUTINE
Ø36Ø ØØØØ	JUMP,	ØØØØ		/ADDRESS OF NEXT SUBROUTINE
Ø361 ØØØØ	RJUM,	ØØØØ		/RESET FOR DON'T UNDERSTAND ETC.
Ø362 ØØØØ	CHAR,	ØØØØ		/HOLDS INPUT CHARACTER
Ø363 ØØØØ	INDI,	ØØØØ		/HOLDS ADDRESS OF KEY CHARACTER
Ø364 Ø1ØØ	KOUA,	Ø1ØØ		/INPUT CHARACTER ADDRESS
Ø365 Ø1ØØ	RSKA,	Ø1ØØ		/RESET KOUA
Ø366 Ø477	KOUB,	Ø477		/KEY CHARACTER ADDRESS
Ø367 Ø477	RSKB,	Ø477		/RESET KOUB
Ø37Ø 7562	MASA,	7562		/MASK FOR CAR RET
Ø371 7537	MASB,	7537		/MASK FOR SPACE
Ø372 Ø777	MASC,	Ø777		/MASK FOR IGNORE SPACE
Ø373 ØØØØ	KOUC,	ØØØØ		/FOR CHAR COUNT RESTORE
Ø374 ØØØØ	RSKC,	ØØØØ		/RESET KOUC
Ø375 ØØØØ	KOUD,	ØØØØ		/FOR CHARACTER COUNT RESET
Ø376 ØØØØ	RSKD,	ØØØØ		/RESET KOUD

BAAD	Ø325
BEGN	Ø2ØØ
CHAR	Ø362
CONT	Ø3Ø5
DUAL	Ø275
GOOD	Ø33Ø
INDI	Ø363
JUMP	Ø36Ø
KEYS	Ø251
KOUA	Ø364
KOUB	Ø366
KOUC	Ø373
KOUD	Ø375
MASA	Ø37Ø
MASB	Ø371
MASC	Ø372
NEXT	Ø233
OKAY	Ø323
OUTS	Ø354
REST	Ø334
RJUM	Ø361
RSKA	Ø365
RSKB	Ø367
RSKC	Ø374
RSKD	Ø376
STAR	Ø2Ø3
WAIT	Ø2Ø4
WOAH	Ø22Ø
ZERO	Ø262

"DET". VARIABLE DATA "C"

(USE THIS ROUTINE OR "SPELL" ROUTINE)

INPUT SENTENCE

KOUA	CHAR	
0100	0317	O
0101	0310	H
0102	0240	
0103	0311	I
0104	0324	T
0105	0240	
0106	0322	R
0107	0301	A
0110	0316	N
0111	0240	
0112	0215	

COUNTERS

KOUA	0100 - 0112
KOUB	0477 - 0502
KOUC	0600 - 0603
KOUD	0500 - 0502
INDI	04XX

KOUB	INDI
------	------

0500	0400 - 0403
0501	0404 - 0413
0502	0414 - *

KOUC

0600	0400
0601	0404
0602	0414
0603	0000

RESTORE

KEY WORDS

*0500		
0400	0315	M
0401	0331	Y
0402	0240	
0403	0650	→ OUT
0404	0311	I
0405	0324	T
0406	7000	← DUAL
0407	0322	R
0410	0301	A
0411	0316	N
0412	0240	
0413	0650	→ OUT
0414	0000	

TEMP STORE

CHAR	(0301)	EXAMPLE
INDI	(0405)	EXAMPLE

LOCATIONS

0000 } 0177 }	SENTENCE
0200 } 0377 }	PROGRAM
0400 } 0577 }	KEY WORDS
0600 } 0777 }	RESTORE

*EACH WORD HAS A COUNTER

KOUA	INPUT CHAR	ADRSS
KOUB	KEY WORD	ADRSS
KOUC	CHAR COUNT	RESTORE
0500	KEY CHAR	COUNT

0664	0000 0212 3117 2577
0670	0240 0122 0577 0240
0674	0177 0240 0705 1611
0700	2523 0240 0215 0212
0704	0000 0212 2410 0124
0710	0240 1123 0240 2022
0714	0524 2431 0240 0717
0720	1704 0240 2320 0514
0724	1411 1607 0240 0215
0730	0212 0000 0212 3117
0734	2577 0240 0717 1706
0740	0504 0240 2422 3177
0744	0240 0107 0111 1677
0750	0240 0215 0212 0000
0754	0212 2410 0124 0240
0760	1123 0240 0317 2222
0764	0503 2477 0240 0215
0770	0212 0000 0624 0644
0774	0664 0704 0731 0753

- YOU GOOFED TRY AGAIN

1000	1052 1071 1104 1122
1004	1134 1146 1163 1176
1010	1210 1223 1233 1244
1014	1261 1273 1305 1314
1020	1322 1330 1337 1345
1024	1055 1052 1071 1104
1030	1122 1134 1146 1163
1034	1176 1210 1223 1233
1040	1244 1261 1273 1305
1044	1314 1322 1330 1337

"DET" LINK

1050	1345 0000 0315 0301
1054	0323 0323 0301 0303
1060	0310 0325 0323 0305
1064	0324 0324 0323 0240
1070	0606 0324 0305 0316
1074	0316 0305 0323 0323
1100	0305 0305 0240 0606
1104	0320 0305 0316 0316
1110	0323 0331 0314 0326
1114	0301 0316 0311 0301
1120	0240 0611 0315 0311
1124	0303 0310 0311 0307
1130	0301 0316 0240 0617
1134	0315 0311 0323 0323
1140	0317 0325 0322 0311
1144	0240 0617 0315 0311
1150	0323 0323 0311 0323
1154	0323 0311 0320 0320

- MASS

"DET" FONT

- TENN

- PENN

- MICH

- MO

- MISS

1160	0311 0240 0606 0314	-	LA
1164	0317 0325 0311 0323		
1170	0311 0301 0316 0301		
1174	0240 0611 0317 0313	-	OKLA
1200	0314 0301 0310 0317		
1204	0315 0301 0240 0611		
1210	0315 0311 0316 0316	-	MINN
1214	0305 0323 0317 0324		
1220	0301 0240 0617 0310	-	HAWAII
1224	0301 0327 0301 0311		
1230	0311 0240 0606 0327	-	WYO
1234	0331 0317 0315 0311		
1240	0316 0307 0240 0611		
1244	0303 0317 0316 0316	-	CONN
1250	0305 0303 0324 0311		
1254	0303 0325 0324 0240		
1260	0606 0304 0305 0314	-	DEL
1264	0301 0327 0301 0322		
1270	0305 0240 0617 0315	-	MD
1274	0301 0322 0331 0314		
1300	0301 0316 0304 0240		
1304	0617 0315 0301 0311	-	MAINE
1310	0316 0305 0240 0617		
1314	0317 0310 0311 0317	-	OHIO
1320	0240 0617 0325 0324	-	UTAH
1324	0301 0310 0240 0617		
1330	0311 0304 0301 0310	-	IDA
1334	0317 0240 0617 0304	-	DUMB
1340	0325 0315 0302 0240		
1344	0603 0000		

